THE BACKUP MASTER

> REEVE SOFTWARE 29W150 OLD FARM LANE WARRENVILLE, IL 60555 (312) 393-2317

PURPOSE-

MANUFACTURER OF THE PROGRAM TO REPLACE IT OR PAY AN UNREASONABLE FEE FOR A BACKUP.

UPDATES-

WE WILL TRY TO PROVIDE UPDATES TO THIS PROGRAM AS NECESSARY AT A REASONABLE COST. ***********

- * LOADING INSTRUCTIONS *
- 1) TURN OFF YOUR COMPUTER, TURN UN YOUR DISK DRIVE, AND TELEVISION 3) DECIDE WHETHER THE PROGRAM YOU OR MONITOR.
- 2) INSERT THE BACKUP MASTER INTO DRIVE NUMBER 1, AND TURN ON YOUR COMPUTER (HOLD DOWN OPTION 4) UNTIL THE SCREEN TURNS BLUE IF BASIC IS NOT DESIRED).
- 3) THE PROGRAM SHOULD LOAD AND SECTOR MAP).
 GREET YOU WITH ITS TITLE SCREEN! B) YOUR COMPUTER SHOULD LOAD THE
- 4) IF THE PROGRAM DISK REFUSES TO C) ONCE THE PROGRAM LOADS, YOUR LOAD, OR YOU HAVE PROBLEMS USING IT PLEASE TRY IT OUT ON ANOTHER COMPUTER BEFORE CONTACTING US.

BE SURE TO READ THROUGH THESE INSTRUCTIONS AT LEAST ONCE BEFORE NOTE: THE BEST WAY TO GET A GOOD USING THE BACKUP MASTER!

FOLLOW THESE INSTRUCTIONS STEP BY STEP WHEN USING THE BACKUP MASTER:

- PART OF THE PROGRAM THAT YOU WISH THE BACKUP MASTER WAS DESIGNED TO

 ALLOW USERS TO BACKUP THEIR SOFTWARE

 A DISK, FORMAT A BLANK DISK IN

 SINGLE DENSITY USING ATARI DOS

 SINGLE DENSITY USING ATARI DOS AND THEN USE THE SECTOR COPIER (OPTION 5) PROVIDED AS PART OF THE BACKUP MASTER.
 - 2) FORMAT ANOTHER DISK USING ATARI DOS AS IN STEP 1. LOAD THE BACKUP MASTER, INSERT YOUR NEWLY FORMATTED DISK INTO DRIVE 1, AND SELECT OPTION 1 TO INITIALIZE THE DISK. THIS DISK WILL BE REFERRED TO AS YOUR BOOT LOAD DISK.
 - WANT TO BACKUP REQUIRES BASIC OR NOT, AND RELOAD THE BACKUP MASTER WITH OR WITHOUT BASIC.

- A) PLACE SIDE 1 OF THE PROGRAM THAT YOU WISH TO BACK UP INTO DRIVE 1, AND SELECT OPTION 2 (CREATE
- PROGRAM THAT YOU ARE COPYING.
- DRIVE SHOULD STOP.
- DRIVE SHOULD SIG..

 D) AT THIS TIME INSERT THE BACK SIDE

 THE BACKUP MASTER INTO DRIVE ONE AND PRESS SYSTEM RESET TO LOAD THE PROGRAM THAT SAVES YOUR SECTOR/STATUS MAP ONTO YOUR BOOT LOAD DISK.

SECTOR MAP IS BY WAITING FOR THE PROGRAM TO QUIT LOADING! THE DRIVE MUST STOP BEFORE INSERTING OUR MAP DUMP PROGRAM INTO DRIVE NUMBER 1.

- 5) CREATE A STATUS MAP IN THE SAME WAY THAT YOU CREATED THE SECTOR MAP IN STEP 4 BY USING OPTION 3.
- 6) NOW RELOAD THE BACKUP MASTER, AND USE OPTION 4 TO COPY DATA FROM SIDE 1 OF THE PROGRAM THAT YOU WISH TO COPY TO YOUR BOOT LOAD DISK. W/o \$451 €
- 7) TO USE YOUR BACK UP COPY:
 - A) INSERT YOUR BOOT LOAD DISK INTO DRIVE 1.
 - B) SELECT BASIC IF NEEDED, AND LOAD THE PROGRAM IN THE SAME WAY THAT YOU LOAD THE ORIGINAL.
 - C) WHEN YOU GET TO THE POINT THAT YOU STOPPED TO CREATE YOUR SECTOR MAP CHANGE DISKS BY INSERTING YOUR SECTOR COPY OF SIDE 1 OF THE PROGRAM INTO DRIVE 1.
 - * OTHER CHOICES *
- 1) PRESS P TO DIS-ENGAGE PRO*MODE!
 YOU WILL THEN SEE A MINUS SIGN
 APPEAR. THIS MAY BE NECESSARY
 FOR A FEW PROGRAMS.
- 2) USING TWO DRIVES:
 YOU CAN USE TWO DISK DRIVES BY
 PRESSING D (FOR DRIVES). THIS
 CHOICE IS USED BY OPTIONS 4 AND
 5.
 - A) WHEN USING TWO DRIVES WITH
 OPTION 4 YOU WILL FIRST BE ASKED
 TO PLACE YOUR BOOT LOAD DISK
 INTO DRIVE 1. AFTER YOUR PRESS
 START AND THE SECTOR MAP HAS
 LOADED INTO MEMORY YOU SHOULD
 THEN MOVE YOUR BOOT LOAD DISK TO
 DRIVE 2, AND PLACE SIDE 1 OF THE
 PROGRAM YOU WISH TO COPY INTO
 DRIVE 1.

B) WHEN USING TWO DRIVES WITH OPTION 5 PLACE YOUR SOURCE DISK IN DRIVE 1, AND YOUR DESTINATION (BLANK FORMATTED) DISK INTO DRIVE TWO.

PLEASE DO NOT ABUSE THE POWER OF THIS PROGRAM!

WARRANTY-

IF THE BACKUP MASTER IS FOUND TO BE DEFECTIVE WITHIN THIRTY DAYS OF PURCHASE PLEASE RETURN IT TO US WITH YOUR COMPLETED WARRANTY CARD, AND A COPY OF YOUR RECEIPT. WE WILL IMMEDIATELY SEND OUT A REPLACEMENT. IF THE BACKUP MASTER FAILS TO WORK AFTER THIRTY DAYS THERE IS A \$2 SERVICE CHARGE. THIS WARRANTY ONLY APPLIES SO LONG AS THE DISK HAS BEEN TREATED PROPERLY.